How to make Vista work with this adapter - Part#RR-527950

Released: April 3, 2009

Steps to resolve this issue

1. Click start and type "regedit" and press enter to bring up the Registry Editor.

	Type the name of a program, folder, document, or Internet resource, and Windows will open it for you.				
pen:	regedit				

NOTE: User Account Control may ask for permission to continue, if so, dick continue.



2. In Registry Editor, scroll to the top, left side of the left Window pane – and then navigate to: Click **HKEY_LOCAL_MACHINE**

Then s croll down and dick **Software** Then s croll down and dick **Microsoft** Then s croll down and dick **Windows** Then s croll down and dick **CurrentVersion**





Next Page

File Edit View Favorites Help				
WAB WBEM Web Folders Web Senice Providers Windows CurrentVersion App Management App Paths Applets Authentication BITS Component Based	i Se	Name (Default) (Default) (Default) DevicePath MediaPathUnexpanded PF_AccessoriesName ProgramFilesDir ProgramFilesPath SM_AccessoriesName SM_ConfigureProgramsName SM_GamesName	Type REG_SZ REG_SZ REG_EXPAND_SZ REG_EXPAND_SZ REG_SZ REG_SZ REG_SZ REG_SZ REG_SZ REG_SZ REG_SZ	Data C:\Program Files\C %SystemRoot%\int %SystemRoot%\M Accessories C:\Program Files %ProgramFiles% Accessories Set Program Access Games
	*	۰ (m		*

- 3. In the details pane, double-dick Device Path.
- 4. Add a semi-colon to end of the existing text, and then add the path to %SystemRoot%\System32. The result should be similar to: %SystemRoot%\inf;%SystemRoot%\System32

Do not remove the %SystemRoot%\inf file path from the DevicePath registry entry.

×
ot%\System32
OK Cancel

- 5. Click OK to save the new value, and then dose Registry Editor.
- 6. If the cable is plugged in, unplug the cable, reboot the computer, plug it back in after reboot, then you will be able to use the adapter.

Sources: Microsoft TechNet, vistabugfixes.blogspot.com

If you have any questions, feel free to call our toll free tech support hotline at 877-522-3779 ext. 2.

www.USBFireWire.com 209 E. William, Suite 510 Wichita, KS 67202